

PPTP сервер

Установить пакеты:

```
rpm -Uvh http://download.fedoraproject.org/pub/epel/beta/7/x86_64/epel-release-7-1.noarch.rpm
yum -y install ppp pptpd
```

Настроить конфиги PPTP сервера:

```
cp /etc/pptpd.conf /etc/pptpd.conf.bak
cat >/etc/pptpd.conf<<EOF
option /etc/ppp/options.pptpd
logwtmp
localip 10.0.10.1
remoteip 10.0.10.2-254
EOF

cp /etc/ppp/options.pptpd /etc/ppp/options.pptpd.bak
cat >/etc/ppp/options.pptpd<<EOF
name pptpd
refuse-pap
refuse-chap
refuse-mschap
require-mschap-v2
require-mppe-128
proxyarp
lock
nobsdcomp
novj
novjccomp
nologfd
ms-dns 8.8.8.8
ms-dns 8.8.4.4
EOF

cp /etc/ppp/chap-secrets /etc/ppp/chap-secrets.bak
cat >/etc/ppp/chap-secrets<<EOF
```

```
USERNAME pptpd PASSWORD *  
EOF
```

Настроить sysctl:

```
cp /etc/sysctl.conf /etc/sysctl.conf.bak  
cat >/etc/sysctl.conf<<EOF  
net.core.wmem_max = 12582912  
net.core.rmem_max = 12582912  
net.ipv4.tcp_rmem = 10240 87380 12582912  
net.ipv4.tcp_wmem = 10240 87380 12582912  
net.core.wmem_max = 12582912  
net.core.rmem_max = 12582912  
net.ipv4.tcp_rmem = 10240 87380 12582912  
net.ipv4.tcp_wmem = 10240 87380 12582912  
net.core.wmem_max = 12582912  
net.core.rmem_max = 12582912  
net.ipv4.tcp_rmem = 10240 87380 12582912  
net.ipv4.tcp_wmem = 10240 87380 12582912  
net.ipv4.ip_forward = 1  
EOF  
sysctl -p
```

Настроить фаервол:

```
chmod +x /etc/rc.d/rc.local  
echo "iptables -t nat -A POSTROUTING -s 10.0.10.0/24 -o eth0 -j MASQUERADE" >>  
/etc/rc.d/rc.local  
iptables -t nat -A POSTROUTING -s 10.0.10.0/24 -o eth0 -j MASQUERADE
```

Запустить сервис:

```
systemctl enable pptpd.service  
systemctl start pptpd
```

Revision #1

Created 2021-12-19 18:26:15 UTC by Ivan Tiukov

Updated 2024-01-10 01:23:26 UTC by Ivan Tiukov