

Установка ГОСТЕВЫХ СИСТЕМ

- [Alpine Linux](#)
- [Arch Linux](#)
- [CentOS](#)
- [Ubuntu](#)

Alpine Linux

```
sudo apk update
sudo apk upgrade
sudo apk add hvtools
sudo rc-update add hv_fcopy_daemon
sudo rc-update add hv_kvp_daemon
sudo rc-update add hv_vss_daemon
sudo rc-service hv_fcopy_daemon start
sudo rc-service hv_kvp_daemon start
sudo rc-service hv_vss_daemon start
sudo reboot
```

Arch Linux

```
sudo pacman -Suyy  
sudo reboot  
sudo pacman -S hyperv  
% for i in {vss,fcopy,kvp}; do sudo systemctl enable hv_${i}_daemon.service; done  
sudo reboot
```

CentOS

```
sudo yum upgrade
sudo reboot
sudo echo "SUBSYSTEM==\"memory\", ACTION==\"add\", ATTR{state}==\"online\"" > /etc/udev/rules.d/100-
balloon.rules
sudo yum install hyperv-daemons
sudo echo noop > /sys/block/sda/queue/scheduler
sudo systemctl enable hypervkvpd hypervvssd hypervfcopyd
sudo nano /etc/default/grub
```

“ GRUB_CMDLINE_LINUX="... elevator=noop"

```
sudo grub2-mkconfig -o /boot/grub2/grub.cfg
sudo grub2-mkconfig -o /boot/efi/EFI/centos/grub.cfg
sudo reboot
```

Ubuntu

```
sudo apt update && sudo apt upgrade
sudo reboot
sudo apt install --install-recommends linux-virtual linux-tools-virtual linux-cloud-tools-virtual
sudo echo "hv_vmbus" >> /etc/initramfs-tools/modules
sudo echo "hv_storvsc" >> /etc/initramfs-tools/modules
sudo echo "hv_blkvsc" >> /etc/initramfs-tools/modules
sudo echo "hv_netvsc" >> /etc/initramfs-tools/modules
sudo rmmod floppy
echo "blacklist floppy" | sudo tee /etc/modprobe.d/blacklist-floppy.conf
sudo update-initramfs -u
sudo reboot
```